

ADP Gateway API Documentation

John Machado

May 2025

Contents

1	Introduction	4
2	Read Screens	5
2.1	Endpoint	5
2.2	Method	5
2.3	Payload	5
2.3.1	Valid Values	5
2.4	Returned Data	6
3	Update Screens	7
3.1	Endpoint	7
3.2	Method	7
3.3	Payload	7
3.3.1	Valid Values	8
3.4	Returned Data	11
4	Remove Screens	12
4.1	Endpoint	12
4.2	Method	12
4.3	Payload	12
4.3.1	Valid Values	12
4.4	Returned Data	12
5	Remove All Screens	13
5.1	Endpoint	13
5.2	Method	13
5.3	Payload	13
5.3.1	Valid Values	13
5.4	Returned Data	13
6	Read Playlist	14
6.1	Endpoint	14
6.2	Method	14
6.3	Payload	14
6.3.1	Valid Values	14
6.4	Returned Data	14
7	Update Playlist	15
7.1	Endpoint	15
7.2	Method	15
7.3	Payload	15
7.3.1	Valid Values	15
7.4	Returned Data	15

8	Remove from Playlist	16
8.1	Endpoint	16
8.2	Method	16
8.3	Payload	16
8.3.1	Valid Values	16
8.4	Returned Data	16
9	Remove All from Playlist	17
9.1	Endpoint	17
9.2	Method	17
9.3	Payload	17
9.3.1	Valid Values	17
9.4	Returned Data	17
10	Settings Read	18
10.1	Endpoint	18
10.2	Method	18
10.3	Payload	18
10.3.1	Valid Values	18
10.4	Returned Data	18
11	Settings Update	19
11.1	Endpoint	19
11.2	Method	19
11.3	Payload	19
11.3.1	Valid Values	19
11.4	Returned Data	20

1 Introduction

A REST API has been implemented to facilitate automated access to the sign's database. REST APIs are widely supported in all programming languages. For more information visit POSTMAN's REST API primer.

REST APIs facilitate sign automation.



They are analogous to user interfaces for humans.



2 Read Screens

Returns all screen data.

2.1 Endpoint

`.../screens/read`

2.2 Method

`GET`

2.3 Payload

NOT REQUIRED

2.3.1 Valid Values

NOT APPLICABLE

2.4 Returned Data

database data

```
{
  "screens": {
    "screen_id": {
      "vertical_alignment": string,
      "rows": {
        "row_id": {
          "font_size": string,
          "font_weight": string,
          "hold_time": string,
          "horizontal_alignment": string,
          "in_mode": string,
          "scroll_speed": string,
          "segments": {
            "segment": {
              "foreground_color": string,
              "background_color": string,
              "flash": string,
              "text": string
            }, ...
          }, ...
        }, ...
      }, ...
    }, ...
  }, ...
}
```

3 Update Screens

A screen is a collection of rows, which in turn are a collection of segments.

- Screen creation/update database operations are inferred; this is the only endpoint needed.
- The playlist will become the list of screens added by this operation.

3.1 Endpoint

`.../screens/update`

3.2 Method

`GET`

3.3 Payload

```
{
  "screen_id": {
    "vertical_alignment": string ,
    "rows": {
      "row_id": {
        "font_size": int ,
        "font_weight": string ,
        "hold_time": int ,
        "horizontal_alignment": string ,
        "in_mode": string ,
        "scroll_speed": string ,
        "segments": {
          "segment_id": {
            "foreground_color": string ,
            "background_color": string ,
            "flash": string ,
            "text": string
          }, ...
        }, ...
      }, ...
    }
  }
}
```

3.3.1 Valid Values

- screens: map of screen
- screen.id: string
 - one to four character length
 - can be any ascii character in range 32,125 inclusive
- screen.vertical_alignment: string
 - aligns all rows vertically
 - options:
 - * top, middle, fill, bottom
- row.id: string
 - screen.id appended with three digit left zero padded row number
 - must be sequential
 - examples:
 - * screen.id = "A":
 1. first row.id = "A000"
 2. second row.id = "A001"
 3. ...
 4. nth row.id = "An" where $n \leq 999$ left zero padded
 - * screen.id = "x434":
 1. first row.id = "x434000"
 2. second row.id = "x434001"
 3. ...
 4. nth row.id = "x434n" where $n \leq 999$ left zero padded
- row.font_size: integer
 - integer
 - font size in pixels
 - normal options:
 - * 5, 7, 9, 11, 14, 15, 16, 22, 24, 30, 32, 40, 64, 71, 80, 88
 - bold options:
 - * 5, 11, 14, 15, 16, 22, 30, 32, 40
- row.font_weight: string
 - options:
 - * bold, normal

- row.hold_time: integer
 - options:
 - * integer in the range 1 to 99 inclusive
- row.horizontal_alignment: string
 - options:
 - * left, center, right
- row.in_mode: string
 - options:
 - * hold, scroll
- row.scroll_speed: string
 - options:
 - * slowest, slow, normal, fast, fastest
- segment.id: string
 - row.id appended with three digit left zero padded segment number
 - must be sequential
 - examples:
 - * row.id = "A000":
 1. first segment.id = "A000000"
 2. second segment.id = "A000001"
 3. ...
 4. nth segment.id = "A000{n}" where $n \leq 999$ left zero padded
 - * row.id = "x434000000"
 1. first segment.id = "x434001000"
 2. second segment.id = "x434001001"
 3. ...
 4. nth segment.id = "x434001{n}" where $n \leq 999$ left zero padded
- segment.foreground_color: string
 - options:
 - * black, red, green, blue, yellow, white
- segment.background_color: string
 - options:
 - * black, red, green, blue, yellow, white, or 6 digit hex value preceded by #

- flash: string
 - options:
 - * on, off
- text: string
 - options:
 - * ascii characters in the range 32 to 125 inclusive

3.4 Returned Data

user submission

```
{
  "screen_id": {
    "vertical_alignment": string,
    "rows": {
      "row_id": {
        "font_size": string,
        "font_weight": string,
        "hold_time": string,
        "horizontal_alignment": string,
        "in_mode": string,
        "scroll_speed": string,
        "segments": {
          "segment_id": {
            "foreground_color": string,
            "background_color": string,
            "flash": string,
            "text": string
          }, ...
        }, ...
      }, ...
    }
  }
}
```

4 Remove Screens

Delete screens from the signs database and playlist

4.1 Endpoint

.../screens/delete

4.2 Method

GET

4.3 Payload

```
{
  [
    string ,
    ... ,
    string
  ]
}
```

4.3.1 Valid Values

- Array elements must be valid screen ids.

4.4 Returned Data

user submission

```
{
  "removed_screens": [
    string ,
    ... ,
    string
  ]
}
```

5 Remove All Screens

Removes all screens from both the database and the playlist.

5.1 Endpoint

`.../screens/delete_all`

5.2 Method

GET

5.3 Payload

NOT REQUIRED

5.3.1 Valid Values

NOT APPLICABLE

5.4 Returned Data

"all screens deleted"

6 Read Playlist

Returns all playlist data.

6.1 Endpoint

.../playlist/read

6.2 Method

GET

6.3 Payload

NOT REQUIRED

6.3.1 Valid Values

NOT APPLICABLE

6.4 Returned Data

database data

```
{
  "playlist": [
    string ,
    ... ,
    string
  ]
}
```

7 Update Playlist

The playlist is the list of screens that will be shown sequentially. The interval between screens is determined by the HOLD TIME option and any overflow condition.

- Updating the playlist will replace the old playlist with the new one.
- Removing screen ids from the playlist will not remove the screen data from the database.

7.1 Endpoint

.../playlist/update

7.2 Method

GET

7.3 Payload

```
{
  [
    string ,
    ... ,
    string
  ]
}
```

7.3.1 Valid Values

- array where elements must be valid screen ids

7.4 Returned Data

user submission

```
{
  "updated_playlist": [
    string ,
    ... ,
    string
  ]
}
```

8 Remove from Playlist

Removes entries from the playlist.

8.1 Endpoint

.../playlist/delete

8.2 Method

GET

8.3 Payload

The screen ids of screens that should be removed from the signs database.

```
{
  [
    string ,
    ... ,
    string
  ]
}
```

8.3.1 Valid Values

- array where elements must be valid screen ids

8.4 Returned Data

user submission

```
{
  "removed_from_playlist": [
    string ,
    ... ,
    string
  ]
}
```


9 Remove All from Playlist

Removes all playlist entries.

9.1 Endpoint

`.../playlist/delete_all`

9.2 Method

GET

9.3 Payload

NOT REQUIRED

9.3.1 Valid Values

NOT APPLICABLE

9.4 Returned Data

`"playlist - deleted"`

10 Settings Read

Read values of sign settings.

10.1 Endpoint

.../settings/read

10.2 Method

GET

10.3 Payload

NOT REQUIRED

10.3.1 Valid Values

NOT APPLICABLE

10.4 Returned Data

database data

```
{
  "brightness": string ,
  "dimensions": {
    "width": string ,
    "height": string
  }
}
```

11 Settings Update

Update settings values.

11.1 Endpoint

`.../settings/update`

11.2 Method

GET

11.3 Payload

Each setting is sufficient to perform an update but all setting parameters are necessary. For example, dimensions can be updated by itself, but both width and height will need to be provided for the update to take effect.

```
{
  ?"brightness": real ,
  ?"dimensions": {
    "width": integer ,
    "height": integer
  }
}
```

11.3.1 Valid Values

- brightness: real
 - real number in range 0 and 1 inclusive
 - example: 0.5
- dimensions.width: integer
 - represents the width of the sign in pixels.
 - example: 100
- dimensions.height: integer
 - represents the width of the sign in pixels.
 - example: 25

11.4 Returned Data

user submission

```
{
  ? "brightness": string ,
  ?"dimensions": {
    "width": string ,
    "height": string
  }
}
```